



## Adobe Premiere Uninstall Procedure

Here is what to do when trying to un-install both Premiere versions from your computer:

1. First un-install your Canopus capture card's software and all your Canopus software plug-ins (ex Xplode Professional, Xplode Basics, 3DRT, etc) by going to Start Button-> Programs-> Your canopus capture card and Canopus Software plug-ins-> Un-install.
  - You do not need to un-install your Canopus Capture card's driver. Only the software...(unless you are wanting to upgrade to newer drivers)
  - If you do not find the un-install utility, you can go to Add/Remove Programs and un-install from there. Select all components for un-install...
2. Next, un-install both Premiere versions 6.0 and 6.5 or whichever is currently installed, by going to Start button->Programs-> Adobe-> Premiere-> Un-install...
3. Next, DELETE from your C:\Program Files\Adobe directory, both the "Premiere 6.0 and Premiere 6.5" sub-folders only...
  - If you originally installed Premiere on a different drive and/or different location other than Premiere's default install location, please locate those Premiere installed folders and delete them.
  - If you have any Project files/ AVIs in those folders, please backup those files to another area FIRST, before deleting.
4. Next, DELETE from your C:\Program Files\Canopus directory, the "3DRT", "Xplode Professional", "Xplode Basics", and "Xplode Demo" sub-folders only, if any.
5. Next, go to Start button-> Run.
  - In the box, type the following "RegEdit" and Click the ENTER and/or OK button...
6. Once the RegEdit utility window appears, look for Hkey\_Local Machine root folder-> Software-> Adobe.
  - You will see a list of subfolders below. Right-click and delete any Premiere 6.0 and 6.5 Subfolders only...
7. Next, Look for Hkey\_current Users root folder-> Software-> Adobe.
  - Again you MIGHT see a list of subfolders. Right-click and delete the Premiere 6.0 and 6.5 sub-folders only, if any...
8. Next, look for Hkey\_Local Machine root folder-> Software-> Canopus.
  - You will see a list of subfolders below. Right-click and delete any Xplode and/or 3DRT sub-folders only ...
9. Next, Look for Hkey\_current Users root folder-> Software-> Canopus.
  - Again you MIGHT see a list of subfolders. Right-click and delete any Xplode and/or 3DRT sub-folders only, if any...
10. Exit the RegEdit utility...
11. Reboot PC...
12. Re-install Premiere 6.5...
13. Re-install your Canopus Capture card's software and/or drivers and Canopus Software Plug-ins by re-running SETUP.EXE from the Canopus capture card software CD and/or downloaded drivers folder.
  - Make sure that during setup, that the components "Prem 5.x" and/or "Prem 6.x" plug-ins are selected...



14. Start Premiere 6.5-> Select the "Canopus DV NTSC" project settings preset (if you use our Canopus Capture card) or any other preferred preset for your capture card-> go to Edit menu-> Preferences->Scratch disks/ device control.
  - Set the Device control for your Canopus Capture card and/ or other device.

**You now should be able to edit in Premiere and have options for our software plug-ins accessible.**